

PUYALLUP PUBLIC LIBRARY

How to Transfer eBooks to a Nook

How eBook borrowing works:

- eBooks work like normal library books. The library owns a copy of each eBook. When that copy is checked out it will say "Request this Item", indicating that you need to wait for the previous patron to finish reading it.
- If a copy is available it will say "Add to Cart" and you will be able to add it to your cart, check it out and download the eBook.
- eBooks automatically expire after the lending period is complete. You may select either a 14 or 21 day loan period when you checkout.
- You may have 5 downloadable items out at a time. This includes both eBooks and audiobooks (5 total).

Brief Instructions for the Tech Savvy:

1. Click on the link to Washington Anytime Library on Puyallup Public Library's website, or go to: anytime.lib.overdrive.com
2. Install Adobe Digital Editions from Overdrive.
3. Activate Adobe Digital Editions with an Adobe ID.
4. Connect your Nook to your computer. Activate it with the same Adobe ID.
5. Check out a book on Overdrive. Download it to Adobe Digital Editions.
6. Drag and drop the book onto your Nook.
7. In your Nook, go to "My Library" and then to "Digital Downloads".
8. Read your new book on your Nook!

Detailed Instructions

Step 1: Setup your computer to work with our eBook provider, Overdrive:

1. Go to the Puyallup Public Library website www.puyalluplibrary.org and click on "Download Audiobooks & eBooks" under the Quick Links, or, go to anytime.lib.overdrive.com
2. On the left-hand side under GET STARTED, click on "Quick Start Guide".
3. Scroll down to "Download and install free software" and click on "Download and install Adobe Digital Editions".
4. Download and install Adobe Digital Editions. This software requires Flash.
5. Open up Adobe Digital Editions. It will ask you to activate your software with an Adobe ID.
6. If you create an Adobe ID:
 - a. You may download the book to more than one computer as long as the computers all use the same Adobe ID. (Up to 6 computers can be activated using one Adobe ID).
 - b. You can transfer your eBooks only to Nooks that are using the same Adobe ID.
7. If you decide to continue anonymously:
 - a. You will not be able to transfer eBooks to your Nook!
 - b. You may only download to one computer.

- c. You can activate an Adobe ID at any time. However, you lose the rights to see any eBooks that were downloaded previously.
8. We recommend that you create an Adobe ID. Follow the steps to do so.
9. Activate your Nook by plugging it into your computer with Adobe Digital Editions open.
10. Adobe Digital Editions will detect your Nook and ask to activate it using the same Adobe ID as your copy of Adobe Digital Editions. Follow the prompts (it may take a few minutes for Adobe Digital Editions to see your Nook).

Step 2: Borrowing eBooks on Overdrive:

1. Go to the Puyallup Public Library website www.puyalluplibrary.org and click on "Download Audiobooks & eBooks" under the Quick Links, or, go to anytime.lib.overdrive.com
2. Search for eBooks. You can limit your search to eBooks by clicking on the Advanced Search option and choosing Adobe EPUB eBook from the format drop down box.
3. You can also limit to available copies, by clicking "Only show titles with copies available" from the Advanced Search screen.
4. When doing Quick Searches, your results will show both eBooks and audiobooks. You can tell the difference by checking the type of the book and what they will play on. The first item in the image below is a audiobook. The second is an eBook.
5. To check out a book, click "Add to Cart".
6. Login using your library barcode number (found on the back of your library card) and your PIN (usually the last 4 digits of your telephone number). Proceed to checkout. Confirm checkout.
7. Click download and choose Open with Adobe Digital Editions.

Step 3: Getting your eBook from Adobe Digital Editions onto your Nook:

1. Open Adobe Digital Editions.
2. Plug your Nook into your computer. If you have not previously set it up, Adobe Digital Editions will ask to register your Nook using the same Adobe ID as your Digital Editions.
3. Your Nook will appear on the left under Bookshelves.
4. To transfer your eBook to the Nook, click on your previously downloaded eBook and drag it to the Nook icon on the left. The book will transfer.
5. Unplug your Nook from the computer.
6. To find your new eBook, go to Library and then to My Files. Your new eBook will be in the Digital Editions file.
7. Enjoy!

How to return item early:

1. To return an item early so you may check out another title, hover your mouse over the eBook in Adobe Digital Editions.
2. Click on the Item Options arrow.
3. Click on Return Borrowed Item.

What to do when your eBook expires:

1. When your license to view the eBook expires, you will no longer be able to read the title. However, the data for the eBook will remain on your computer and your Nook until you delete it.
2. To delete the eBook from Adobe Digital Editions, click on the Item Options arrow over the book title and click Delete Item.
3. To delete the eBook from your Nook, click on the Nook icon in Adobe Digital Editions. Click the Item Options arrow and then click Delete Item.

May 19, 2012